



China SMS Login

V1.X for Opencart3

User Guide / *SunflowerBiz*

Table of Contents

1. Installation
2. Module Setting
3. Frontpage
4. Access to Tencent Cloud SMS
5. Access to Alibaba Cloud SMS



SUNFLOWERBIZ

Email: info@sunflowerbiz.com

Web: www.sunflowerbiz.com

Installation:

- Install the module in admin->extensions->installer
- Refresh the modification and theme cache after the installation.
- Enable the module in the module list.



SUNFLOWERBIZ

Email: info@sunflowerbiz.com

Web: www.sunflowerbiz.com

Module Setting:

Configure our module in Dashboard->Extensions->Modules-->China SMS Login.

China SMS Login [Home](#) > [Modules](#) > [China SMS Login](#)

[Edit China SMS Login Module](#)

Enable China SMS Login	Enabled
Select Service	aliyun tencent aliyun
Wait Time	40
Country Code	86 <small>Format: 86,852</small>
App ID / AccessKeyId	111
App Key / AccessKeySecret	22222
SMS Sign	1trest
Login SMS template Id	123456
Login SMS template Params	{code} <small>Format: {code},{wait_time}, should match the SMS template</small>
Default Firstname	testf
Default Lastname	testl
Default Email	{phone}@site.com <small>Default Format: {phone}@site.com</small>
Default Password	123456a

Wait Time: Set the waiting time after sending short messages.

SMS Signature: Required field. Enter the SMS signature in your SMS provider center.

Login SMS template Id: The short message template ID given by your SMS provider. Note: The format for Alibaba cloud SMS is "SMS_XXXXXX".

Login SMS template Params: Enter the parameters in your short message template. The format must be {code} or {code},{wait_time} corresponding to your sms template.

Default Customer FirstName/LastName/Email/Password:

Set a default Customer First Name/Last Name/Email/Password when creating a new customer account.

Front:

Display on Login Page

会员登录

如果您已经是本站会员，请直接登录。

E-Mail 地址/手机号码

密码

[忘记密码](#)

登录

短信登录

86 ▾

发送验证码

登录

 微信登录

 QQ登录

 微博登录

 支付宝登录

Our module will create a Phone field for each customer. After logged in , the system will auto search if the customer exists. If not, it will use the default data to auto create a new customer account.

Tencent Cloud SMS

How to Access to [Tencent Cloud SMS](#):

Step1. Signing up for a Tencent Cloud Account

You need to sign up for a Tencent Cloud account if you don't have one. For more information on registration procedure, please see [Sign up for Tencent Cloud](#).

If you already have a Tencent Cloud account, go to next step.

Step2. Logging in to Tencent Cloud SMS Console

Log in to the Tencent Cloud SMS [Console](#). You need to apply for the activation of SMS upon first login.

Step3. Applying for Activation of SMS

If your account has not gone through identity verification, please go to [Account Center](#) for identity verification. For more information, please see [Identity Verification Guide](#).

If your identity verification is approved, click Access

申请开通

你可以选择[个人认证](#)或[企业认证](#)，不同认证有不同的服务权限

个人认证：认证信息为个人，只能使用国内文本短信，且只支持使用短信套餐包。

企业认证：认证信息为企业或组织，使用全部短信服务，并支持预付费使用。

您当前认证为**个人认证**

如果您想变更认证类型，请到帐户信息中进行 [认证变更](#)。

开始接入

[More info](#)

Alibaba Cloud SMS

[Alibaba Cloud's Short Message Service](#) provides the APIs and SDK to developers to send messages all around the world. The system supports OTP (One-Time-Password), transaction notifications, push notifications and promotional campaigns as well as supports both domestic and international messaging.

Quick Start

Step 1. Select or create your AccessKey.

- ✓ Create and login to an Alibaba Cloud account.
- ✓ Make sure that your account is an enterprise account. If your account is an individual account, upgrade to an enterprise account. Currently, Alibaba Cloud SMS is only available to enterprise accounts.
- ✓ Make sure that you have added a credit card or a PayPal account as the payment method.
- ✓ If you already have an AccessKey, you can use this AccessKey to access Alibaba Cloud SMS. If you do not have an AccessKey, or want to use a new AccessKey, you can create one.

Step 2. Activate Alibaba Cloud SMS and purchase SMS packages.

- ✓ Activate Alibaba Cloud SMS.
- ✓ You need to purchase an SMS package before you can use SMS.

Step 3. Configure parameters

- ✓ The system supports the creation of different SMS content for use in different business scenarios. SMS content can contain custom parameters.
- ✓ Configure the method to receive message status.
- ✓ In the SMS console, configure the message sending frequency and alarm threshold for the number of sent messages.
- ✓

Step 4. Download the required SDK, configure API parameters

- ✓ Download the required SDK.
- ✓ Import the SDK to your project, and configure the parameters specified in the sample code. Learn more about API parameters.
- ✓ Send a test message and view the delivery result. Each Alibaba Cloud account can send 100 messages free of charge.

[More info](#)